

7.1.31 Editors - 3D View - Header - Grease Pencil - Edit mode - Stroke menu


Edit Mode - Stroke Menu.....	2
Subdivide.....	2
Last Operator Subdivide.....	2
Number of Cuts.....	2
Smooth.....	2
Repeat.....	2
Selected Points.....	2
Position.....	2
Thickness.....	2
Strength.....	3
UV.....	3
Simplify.....	3
Fixed.....	3
Last Operator Simplify Fixed Stroke.....	3
Steps.....	3
Adaptive.....	3
Last Operator Simplify Stroke.....	3
Factor.....	3
Sample.....	3
Last Operator Sample Stroke.....	3
Factor.....	3
Trim.....	3
Join.....	4
Join and copy.....	4
Last Operator Join Strokes.....	4
Type.....	4
Leave Gaps.....	4
Move to Layer.....	4
New Layer.....	4
Last Operator Move Strokes to Layer.....	4
Grease Pencil Layer.....	4
Assign Material.....	5
Last Operator Change Stroke Color.....	5
Material.....	5
Set as active material.....	5
Arrange.....	5
Bring Forward.....	5
Send Backward.....	5
Bring to Front.....	5
Send to Back.....	6
Last Operator Arrange Stroke.....	6
Direction.....	6
Close.....	6
Toggle Cyclic.....	6
Last Operator Set Cyclical State.....	6
Type.....	6
Close all.....	6
Open all.....	6
Toggle.....	6

Create geometry.....	6
Toggle Caps.....	6
Default.....	7
Both.....	7
Start.....	7
End.....	7
Last Operator Set Caps Mode.....	7
Type.....	7
Switch Direction.....	7
Re project Strokes.....	7
Last Operator Re project Strokes.....	7
Projection Type.....	7
Reset Fill Transform.....	7

Edit Mode - Stroke Menu

In Edit Mode you will also see a add menu for some object types. The number of objects that you can add is limited to the same object type that you are in edit mode with. You can just add mesh geometry to a mesh geometry. And just curve geometry to curve geometry.

The added objects in edit mode becomes part of the current object geometry.



Subdivide

Subdivides the selected grease pencil geometry.

Last Operator Subdivide

Number of Cuts

Number of subdivision cuts.

Smooth

Smoothen the stroke, not just the new added vertices

Repeat

The number of times to repeat the procedure.

Selected Points


Limits the effect to only the selected points within the stroke.

Position

The operator affects the points location.

Thickness

The operator affect the points thickness.



Strength


The operator affect the points strength (alpha).

UV

The operator affect the UV rotation on the points.

Simplify

Simplifies the stroke.




Fixed

Deletes every second point in the stroke, except the start and end points.

Last Operator Simplify Fixed Stroke

Steps

How much levels of simplifying.



Adaptive

This method uses an algorithm called RDP algorithm (Ramer-Douglas-Peucker algorithm) for points deletion. The algorithm tries to keep the shape with the remaining points.

Last Operator Simplify Stroke

Factor

How strong the simplification should be performed.



Sample

Samples points along the shape of the stroke, and increases the length of the edges.

Last Operator Sample Stroke


Factor

How long the edges between the points should be.



Trim

Trims down selected stroke geometry to first loop or intersection.



Join

Join selected strokes by connecting points.


Join and copy

Join selected strokes by connecting points in a new stroke.

Last Operator Join Strokes

Type

Join or Join and Copy.




Leave Gaps

Don't connect the strokes by geometry.


Move to Layer

Move the current selected stroke to another grease pencil layer. It lists the current layers.




New Layer

New Layer button adds a new grease pencil layer.




Last Operator Move Strokes to Layer



Grease Pencil Layer

Internal the layers are enumerated. So here you move by number.

The number of a layer can be found out in the tool tip, in the Python part of it.




Assign Material

Assign a new material to the current selected stroke geometry.




The materials can be found and edited in the Properties editor. Here you can also create new materials.



Last Operator Change Stroke Color

Material

The materials are defined by its name. So when you want to use another material, then change the name here.




Set as active material

Sets the current selected material as the active material.

Arrange

Changes the drawing order of the strokes in the 2D layer.



Bring Forward

Moves the selected points/strokes upper the next one in the drawing order.

Send Backward

Moves the selected points/strokes below the previous one in the drawing order.

Bring to Front

Moves to the top the selected points/strokes.


Send to Back

Moves to the bottom the selected points/strokes.

Last Operator Arrange Stroke

Direction

Choose the method again.



Close

Closes the current stroke by connecting the first vertice with the last vertice by a stroke. See also Toggle Cyclic.


Toggle Cyclic

When the curve is open, then it Closes the current stroke by connecting the first vertice with the last vertice by a stroke. When the curve is closed, then it removes the connection between first and last vertice, and makes the curve open.

Last Operator Set Cyclical State

Type

Choose the method again.



Close all

Close all open selected strokes.

Open all

Open all closed selected strokes.

Toggle



Close or Open selected strokes as required.

Create geometry

When enabled, points are added for closing the strokes like when using the Close tool. If disabled, the stroke is closed with just one edge.

Toggle Caps

Toggles if the start and endpoints of the strokes are rounded or flat.



Default

Sets stroke start and end points to rounded (default).

Both

Toggle stroke start and end points caps to flat or rounded.

Start

Toggle stroke start point cap to flat or rounded.


End

Toggle stroke end point cap to flat or rounded.

Last Operator Set Caps Mode

Type

Choose the method again.




Switch Direction

Switches the direction of the stroke geometry.

Re project Strokes


Re projects the selected stroke points in the selected view method.



Last Operator Re project Strokes

Projection Type

Choose the method again.



Reset Fill Transform

Reset any UV transformation back to default values.