



26.9.10 Editors - Properties Editor - Modifiers Properties Tab - Modify modifiers

Table of content

Detailed table of content.....	1
Grease Pencil - Modify modifiers.....	2
Texture Mapping.....	3
Time Offset Modifier.....	5
Vertex Weight Angle.....	6
Vertex Weight Proximity.....	8


Detailed table of content

Detailed table of content

Detailed table of content.....	1
Grease Pencil - Modify modifiers.....	2
Texture Mapping.....	3
Mode.....	3
Stroke.....	3
Stroke Fit Method.....	3
Constant Length.....	3
Stroke Length.....	3
UV Offset.....	3
Rotation.....	3
Scale.....	3
Fill.....	3
Fill Rotation.....	3
Offset X / Y.....	3
Scale.....	4
Stroke and Fill.....	4
Influence Subpanel.....	4
Influence.....	4
Layer.....	4
Invert.....	4
Pass.....	4
Invert.....	4
Material.....	4
Invert.....	4
Pass.....	4
Invert.....	4
Vertex Group.....	5
Invert.....	5
Time Offset Modifier.....	5
Mode.....	5
Regular.....	5
Reverse.....	5
Fixed Frame.....	5


Frame Offset.....	5
Scale.....	5
Keep Loop.....	5
Custom Range.....	5
Frame Start / End.....	5
Influence.....	6
Layer.....	6
Invert.....	6
Pass.....	6
Invert.....	6
Vertex Weight Angle.....	6
Vertex Group.....	6
Angle.....	6
Axis.....	6
Space.....	6
Minimum.....	7
Multiply Weights.....	7
Influence Subpanel.....	7
Influence.....	7
Layer.....	7
Invert.....	7
Pass.....	7
Invert.....	7
Material.....	7
Invert.....	7
Pass.....	7
Invert.....	7
Vertex Group.....	7
Invert.....	7
Vertex Weight Proximity.....	8
Vertex Group.....	8
Target Object.....	8
Lowest.....	8
Highest.....	8
Minimum.....	8
Multiply Weights.....	8
Influence Subpanel.....	8
Influence.....	8
Layer.....	8
Invert.....	9
Pass.....	9
Invert.....	9
Material.....	9
Invert.....	9
Pass.....	9
Invert.....	9
Vertex Group.....	9
Invert.....	9

Grease Pencil - Modify modifiers



Texture Mapping

The Texture Mapping Modifier changes the strokes texture UV position.




Mode

The texture transformation will be applied to the stroke/fill or stroke UVs.




Stroke



Stroke Fit Method

The texture fitting method.



Constant Length

The texture keep a consistent length along the strokes.

Stroke Length

The texture is normalized to fit the stroke length.

UV Offset

Moves the texture along the strokes.

Rotation

Rotates the points of the strokes. Note that the Rotation option is limited to a range of -90 to 90 degrees.


Scale

Factor for the texture scale.

Fill

Fill Rotation

Sets the texture angle.



Offset X / Y


Moves the texture origin in x and/or y direction

Scale

Factor for the texture scale.

Stroke and Fill

See both single chapters above.




Influence Subpanel

Influence

Layer

Restricts the effect only to one layer or to any layers that share the same pass index. Click to pick the layer that you want to use.



Invert

Inverts the influence.

Pass

The layer pass index.

Invert

Inverts the influence.

Material

Restricts the effect only to one layer or to any layers that share the same material index. Click to pick the layer that you want to use.

Invert

Inverts the influence.

Pass

The layer pass index.

Invert

Inverts the influence.

Vertex Group


Restricts the effect only to one vertex group. Click to choose the vertex group.

Invert

Inverts the influence.

Time Offset Modifier

Grease Pencil object only. The Time Offset Modifier offsets the position of Grease Pencil keyframes.



Mode

Regular

Offsets keyframes in default animation playback direction (left to right).

Reverse

Offsets keyframes in inverse animation playback direction (right to left).

Fixed Frame

Keep the selected frame fixed and do not change over time.

Frame Offset

Number of frames to offset the original keyframes.

Scale


Evaluation time (in seconds).

Keep Loop

Moves end frame to the animation start to keep animation in a loop.

Custom Range

Use a custom range of frames.




Frame Start / End

Sets the range start and end frames.

Influence

Layer

Restricts the effect only to one layer or to any layers that share the same pass index. Click to pick the layer that you want to use.



Invert

Inverts the influence.

Pass

The layer pass index.

Invert


Inverts the influence.

Vertex Weight Angle

This modifier sets the weights of a vertex group based of the angle of the geometry.

Warning! This modifier does implicit clamping of weight values in the standard (0.0 to 1.0) range. All values below 0.0 will be set to 0.0, and all values above 1.0 will be set to 1.0.

Note! You can view the modified weights in Weight Paint Mode. This also implies that you will have to disable the Vertex Weight Proximity modifier if you want to see the original weights of the vertex group you are editing.



Vertex Group


Which vertex group to use.

Angle

Distance angle to 0.0 weight. Tip! Lowest can be set above Highest to reverse the mapping.


Axis

Which axis to use.



Space

In which space to calculate. Local or Global.



Minimum

Minimum value for vertex weight.

Multiply Weights


Multiply the calculated weights with the existing values of the vertex group.

Influence Subpanel

Influence

Layer

Restricts the effect only to one layer or to any layers that share the same pass index. Click to pick the layer that you want to use.



Invert

Inverts the influence.

Pass

The layer pass index.

Invert

Inverts the influence.

Material

Restricts the effect only to one layer or to any layers that share the same material index. Click to pick the layer that you want to use.

Invert

Inverts the influence.

Pass

The layer pass index.

Invert

Inverts the influence.

Vertex Group

Restricts the effect only to one vertex group. Click to choose the vertex group.

Invert


Inverts the influence.

Vertex Weight Proximity

This modifier sets the weights of the given vertex group, based on the distance between the object (or its vertices), and another target object (or its geometry).

Warning1 This modifier does implicit clamping of weight values in the standard (0.0 to 1.0) range. All values below 0.0 will be set to 0.0, and all values above 1.0 will be set to 1.0.

Note! You can view the modified weights in Weight Paint Mode. This also implies that you will have to disable the Vertex Weight Proximity modifier if you want to see the original weights of the vertex group you are editing.



Vertex Group

The vertex group to affect.

Target Object

The object from which to compute distances.

Lowest

Distance mapping to 0.0 weight. Tip! Lowest can be set above Highest to reverse the mapping.

Highest

Distance mapping to 1.0 weight.

Minimum

Minimum value for vertex weight.

Multiply Weights


Multiply the calculated weights with the existing values of the vertex group.

Influence Subpanel

Influence

Layer

Restricts the effect only to one layer or to any layers that share the same pass index. Click to pick the layer that you want to use.



Invert

Inverts the influence.

Pass

The layer pass index.

Invert

Inverts the influence.

Material

Restricts the effect only to one layer or to any layers that share the same material index. Click to pick the layer that you want to use.

Invert

Inverts the influence.

Pass

The layer pass index.

Invert

Inverts the influence.

Vertex Group

Restricts the effect only to one vertex group. Click to choose the vertex group.

Invert

Inverts the influence.