



7.1.13 Editors - 3D Viewport - Header - Mesh - Edit mode - UV menu

Table of content

| | |
|---------------------------------|---|
| Detailed Table of content..... | 1 |
| Edit Mode - UV Menu..... | 3 |
| Unwrap ABF..... | 3 |
| Unwrap Conformal..... | 3 |
| Smart UV Project..... | 4 |
| Lightmap Pack..... | 4 |
| Follow Active Quads..... | 5 |
| Cube Projection..... | 5 |
| Cylinder Projection..... | 6 |
| Sphere Projection..... | 6 |
| Project from View..... | 7 |
| Project from View (Bounds)..... | 7 |
| Mark Seam..... | 7 |
| Clear Seam..... | 8 |
| Reset..... | 8 |

Detailed Table of content

Detailed table of content


| | |
|---|---|
| Detailed Table of content..... | 1 |
| Edit Mode - UV Menu..... | 3 |
| Unwrap ABF..... | 3 |
| Unwrap Conformal..... | 3 |
| Last Operator Unwrap..... | 3 |
| Method..... | 3 |
| Fill Holes..... | 3 |
| Correct Aspect..... | 3 |
| Use Subsurf Modifier..... | 3 |
| Margin..... | 3 |
| Smart UV Project..... | 4 |
| Smart UV Project Settings dialogue..... | 4 |
| Angle Limit..... | 4 |
| Island Margin..... | 4 |
| Area Weight..... | 4 |
| Correct Aspect..... | 4 |
| Last Operator Smart UV Project..... | 4 |
| Lightmap Pack..... | 4 |
| Settings..... | 4 |
| Selection..... | 4 |
| Share Tex Space..... | 4 |
| New UV Map..... | 4 |
| New Image..... | 4 |
| Image Size..... | 5 |

| | |
|--|---|
| Pack Quality..... | 5 |
| Margin..... | 5 |
| Follow Active Quads..... | 5 |
| Settings..... | 5 |
| Edge Length Mode..... | 5 |
| Last Operator Follow Active Quads..... | 5 |
| Cube Projection..... | 5 |
| Last Operator Cube Projection..... | 5 |
| Cube Size..... | 5 |
| Correct Aspect..... | 5 |
| Clip to Bounds..... | 5 |
| Scale to Bounds..... | 5 |
| Cylinder Projection..... | 6 |
| Last Operator Cylinder Projection..... | 6 |
| Direction..... | 6 |
| Align..... | 6 |
| Radius..... | 6 |
| Correct Aspect..... | 6 |
| Clip to Bounds..... | 6 |
| Scale to Bounds..... | 6 |
| Sphere Projection..... | 6 |
| Last Operator Sphere Projection..... | 6 |
| Direction..... | 6 |
| Align..... | 6 |
| Correct Aspect..... | 6 |
| Clip to Bounds..... | 6 |
| Scale to Bounds..... | 7 |
| Project from View..... | 7 |
| Last Operator Project from View..... | 7 |
| Orthographic..... | 7 |
| Camera Bounds..... | 7 |
| Correct Aspect..... | 7 |
| Clip to Bounds..... | 7 |
| Scale to Bounds..... | 7 |
| Project from View (Bounds)..... | 7 |
| Mark Seam..... | 7 |
| Clear Seam..... | 8 |
| Reset..... | 8 |

Edit Mode - UV Menu

Here you find the uv mapping methods and some further functionality. You use it best in the U Editing layout. There you can see the result in the UV Editor then.

The UV menu is just available for Mesh objects.



Unwrap ABF

Unwrap ABF unwraps the selected geometry with the method Angle based. ABF stands for Angle Based Flattening. ABF can give a bit better result than LSCM when unwrapping organic shapes.

Unwrap Conformal


Unwrap Conformal unwraps the selected geometry with the method LSCM, which is the short for Least Square Conformal Mapping. LSCM can give a bit better results than ABF with geometric shapes.

Last Operator Unwrap

Unwrap ABF and Unwrap LSCM shares the same Last Operator.

Method

Method is a drop down box where you can choose between Unwrap method Angle Based and Conformal.



Fill Holes

Fill holes in the mesh before unwrapping.

Correct Aspect

Take the Image Aspect Ratio into account.

Use Subsurf Modifier

Unwraps an existing Subsurf Modifier. You need to add a Subsurf Modifier first.

Margin

The distance between the single UV patches.

Smart UV Project

Smart UV Project projects the UV mapping from different angles.

Smart UV Project Settings dialogue

Angle Limit

The Angle Limit defines after which angle the mapping happens from the next side. With an angle of 66 you have around six sides to map from. The calculation is $360/66$.

Island Margin


Island Margin defines the distance between the UV patches.

Area Weight

Weight Projection Vector by faces with larger areas.


Correct Aspect

Take the Image Aspect Ratio into account.



Last Operator Smart UV Project

The Last Operator for Smart UV Project contains the same settings than the Smart UV Project Settings dialogue.



Lightmap Pack

Lightmap Pack maps each face individually, and puts the result into the UV space. Without margin.

Lightmap Pack has no Last Operator.

Settings

Selection

Selection is a drop-down box where you can choose what will be packed.

Share Tex Space

Map all objects into one lightmap.

New UV Map

Create a new UV map for every new mesh.

New Image

Assign new Image to every new mesh.




Image Size

The size for new images.

Pack Quality

The pack quality.

Margin

The distance between the single UV patches.


Follow Active Quads

Follow Active quads maps UV coordinates starting from an active face, and maps all adjacent faces in quad shape then. This way you can for example unwrap a pipe or a road. You first need to have a face selected. Then select everything. And then click at Follow Active Quads.

Settings


Edge Length Mode

Edge Length Mode is a drop-down box where you can choose the Length method.



Last Operator Follow Active Quads

The Last Operator contains the same settings than the Settings dialogue.



Cube Projection

Cube Projection maps the mesh from six sides, means cubic.

Last Operator Cube Projection

Cube Size

Cube Size defines the size of the UV mesh in the UV space.

Correct Aspect


Take Image Aspect ratio into account.

Clip to Bounds

Clip UV Coordinates to bounds after unwrapping.

Scale to Bounds

Scale UV Coordinates to bounds after unwrapping.




Cylinder Projection

Cylinder Projection tries to map the geometry cylindrical.

Last Operator Cylinder Projection

Direction

Direction is a drop-down box where you can choose in which direction the cylindrical projection will be mapped.



Align

Align is a drop-down box where you can choose the Align method.

Radius

Radius defines the Polar size of the UV mesh in the UV space.

Correct Aspect

Take Image Aspect ratio into account.

Clip to Bounds

Clip UV Coordinates to bounds after unwrapping.

Scale to Bounds

Scale UV Coordinates to bounds after unwrapping.


Sphere Projection

Sphere Projection tries to map the geometry spherical.

Last Operator Sphere Projection


Direction

Direction is a drop-down box where you can choose in which direction the spherical projection will be mapped.



Align

Align is a drop-down box where you can choose the Align method.



Correct Aspect

Take Image Aspect ratio into account.

Clip to Bounds

Clip UV Coordinates to bounds after unwrapping.



Scale to Bounds

Scale UV Coordinates to bounds after unwrapping.


Project from View

Project from View projects the UV from the current 3D view.

Last Operator Project from View

Orthographic

User orthographic projection.



Camera Bounds

Map UV's to the camera region taking resolution and aspect into account.

Correct Aspect

Take Image Aspect ratio into account.

Clip to Bounds

Clip UV Coordinates to bounds after unwrapping.

Scale to Bounds

Scale UV Coordinates to bounds after unwrapping.

Project from View (Bounds)

Project from View projects the UV from the current 3D view.


Same as Project from View, but with Scale to Bounds ticked in the Last operator. And so it scales to the bounds.

Mark Seam

The unwrap algorithms Angle based and Conformal requires to have edges marked as seams. Think of it as a cutting pattern for a trouser for example. Such a trouser is also made of fabric patterns.

Same goes for the UV patches when you use Angle based or conformal unwrapping. You need to cut your mesh into parts and mark edges as seams, so that the algorithm knows where the seams are.

Mark seam marks the currently selected edge(s) as a seam. Seam edges will be displayed as red in the 3D viewport.



Clear Seam

Clear seam removes the seam from the currently selected edge(s).

Reset

Resets the UV Projection.