

## 7.1.39 Editors - 3D Viewport - Header - Armature - Pose mode - Pose menu

### Table of content

Detailed Table of content.....	1
Pose Mode - Pose Menu.....	5
Clear Transform.....	5
Clear Transform.....	5
Apply.....	6
Apply Pose as Rest Pose.....	6
Apply Selected as Rest Pose.....	6
Apply Visual Transform to Pose.....	6
Assign Custom Property Values as Default.....	6
Snap.....	7
Last Operator Snap.....	7
Animation.....	7
In-Between.....	8
Header values.....	8
Footer hotkey display.....	8
Push Pose from Rest Pose.....	8
Relax Pose to Rest Pose.....	9
Push Pose from Breakdown.....	9
Relax Pose to Breakdown.....	10
Propagate.....	11
Last Operator Propagate Pose.....	12
Single Operators.....	13
Copy Pose.....	13
Paste Pose.....	13
Paste Pose Flipped.....	13
Pose Library.....	13
Motion Paths.....	15
Bone Groups.....	15
Parent.....	16
Inverse Kinematics.....	17
Constraints.....	18
Names.....	19
Flip Quats.....	20
Change Armature Layers.....	20
Change Bone Layers.....	20
Show/Hide.....	20
Bone Settings.....	21

### Detailed Table of content

#### Detailed table of content

Detailed Table of content.....	1
Pose Mode - Pose Menu.....	5


Clear Transform.....	5
Clear Transform.....	5
All.....	5
Clear User Transforms.....	5
Location.....	5
Rotation.....	6
Scale.....	6
Reset Unkeyed.....	6
Last Operator Clear User Transforms.....	6
Only Selected.....	6
Apply.....	6
Apply Pose as Rest Pose.....	6
Apply Selected as Rest Pose.....	6
Last Operator Apply Pose as Rest Pose.....	6
Selected only.....	6
Apply Visual Transform to Pose.....	6
Assign Custom Property Values as Default.....	6
Last Operator Assign Custom Property Values as Default.....	7
Process data properties.....	7
Process bone properties.....	7
Snap.....	7
Last Operator Snap.....	7
Offset.....	7
Animation.....	7
Insert Keyframe.....	7
Delete Keyframes.....	7
Clear Keyframes.....	7
Change Keying Set.....	7
In-Between.....	8
In Between.....	8
Header values.....	8
Footer hotkey display.....	8
Push Pose from Rest Pose.....	8
Last Operator Push Pose from Rest Pose.....	8
Percentage.....	8
Previous Keyframe.....	8
Next Keyframe.....	9
Channels.....	9
Axis Lock.....	9
Relax Pose to Rest Pose.....	9
Last Operator Relax Pose to Rest Pose.....	9
Percentage.....	9
Previous Keyframe.....	9
Next Keyframe.....	9
Channels.....	9
Axis Lock.....	9
Push Pose from Breakdown.....	9
Last Operator Push Pose.....	10
Percentage.....	10
Previous Keyframe.....	10
Next Keyframe.....	10
Channels.....	10
Axis Lock.....	10

Relax Pose to Breakdown.....	10
Last Operator Relax Pose to Breakdown.....	10
Percentage.....	10
Previous Keyframe.....	10
Next Keyframe.....	10
Channels.....	10
Axis Lock.....	11
Pose Breakdowner.....	11
Last Operator Pose Breakdowner.....	11
Percentage.....	11
Previous Keyframe.....	11
Next Keyframe.....	11
Channels.....	11
Axis Lock.....	11
Propagate.....	11
Last Operator Propagate Pose.....	12
Terminate Mode.....	12
While Held.....	12
To Next Keyframe.....	12
To Last Keyframe.....	12
Before Frame.....	12
Before Last Keyframe.....	12
On Selected Keyframes.....	12
On Selected Markers.....	12
End Frame.....	12
Single Operators.....	13
Copy Pose.....	13
Paste Pose.....	13
Paste Pose Flipped.....	13
Last Operator Paste Pose.....	13
Flipped on X Axis.....	13
On Selected Only.....	13
Pose Library.....	13
Browse Poses.....	13
Last Operator Pose lib Browse Poses.....	13
Pose.....	13
Add Pose.....	14
Add New.....	14
Add New (Current Frame).....	14
Replace Existing.....	14
Last Operator Pose Lib Add Pose.....	14
Frame.....	14
Pose Name.....	14
Rename Pose.....	14
Last Operator Pose Lib Rename Pose.....	14
New Pose Name.....	14
Pose.....	14
Remove Pose.....	14
Last Operator Pose Lib Remove Pose.....	15
Pose.....	15
Motion Paths.....	15
Calculate.....	15
Last Operator Calculate Object Path.....	15

Start.....	15
End.....	15
Bake Location.....	15
Clear.....	15
Bone Groups.....	15
Assign to New Group.....	16
Assign to Group.....	16
Last operator Add Selected to Bone Group.....	16
Bone Group Index.....	16
Remove selected from Bone Groups.....	16
Remove Bone Group.....	16
Parent.....	16
Inverse Kinematics.....	17
Add IK to Bone.....	17
Last Operator Add IK to Bone.....	17
With Targets.....	17
Remove IK.....	17
Constraints.....	18
Add (With Targets).....	18
Copy Constraints to selected Bones.....	18
Clear Pose Constraints.....	19
Names.....	19
Autoname Left/Right.....	19
Autoname Front/Back.....	19
Autoname Top/Bottom.....	19
Last operator Autoname by Axis.....	19
Axis.....	19
Flip Names.....	19
Last operator Flip Names.....	19
Strip Numbers.....	19
Flip Quats.....	20
Change Armature Layers.....	20
Last Operator Change Armature Layers.....	20
Layer.....	20
Change Bone Layers.....	20
Last Operator Change Bone Layers.....	20
Layer.....	20
Show/Hide.....	20
Show Hidden.....	20
Hide Selected.....	20
Hide Unselected.....	21
Bone Settings.....	21
Last Operator Collection Boolean Set.....	21

## Pose Mode - Pose Menu


The Pose menu contains the tools to work with Armature objects in Pose mode. This means here you find all the tools that you need to pose and animate your armature.



## Clear Transform

### Clear Transform

Clear transform is a menu with some Clear functionality. You need to have the bones selected where you want to perform the operation. Unselected bones will not be calculated.



### All

Resets location, rotation and scale back to the Rest pose.

### Clear User Transforms

Resets Pose of selected bones back to keyframe state.

### Location

Resets location back to the Rest pose.

## Rotation

Resets rotation back to the Rest pose.

---

## Scale

Resets scale back to the Rest pose.

---


## Reset Unkeyed

Resets the pose for the selected bones back to the state of the latest keyframe.

## *Last Operator Clear User Transforms*

### Only Selected

Clear User transform for selected armature part, or for the whole armature.




## Apply

Apply is a menu with some Apply functionality.

## Apply Pose as Rest Pose

You need a rest pose where you can reset the pose back to. With this tool you can set the current pose to be the new Rest pose.




## Apply Selected as Rest Pose

You need a rest pose where you can reset the pose back to. With this tool you can set the current pose of the selected bones to be the new Rest pose.

## Last Operator Apply Pose as Rest Pose

### *Selected only*

Just apply the pose to the selected part.



## Apply Visual Transform to Pose

Apply final constrained position of posed bones to their transform.

## Assign Custom Property Values as Default

Assigns the current values of custom properties as their defaults. This allows to use them as part of the rest pose state in NLA track mixing.


## Last Operator Assign Custom Property Values as Default

### *Process data properties*

Include the process data properties.

### *Process bone properties*

Include the process bone properties.



## Snap

Choose several methods to snap one element to another. The menu items should be self explaining.


## Last Operator Snap

Some snap operations shows a last operation panel, some not.




## Offset

If the selection should snap as a whole, or if each individual element of the selection should snap.



## Animation

Animation is a sub menu around animation functionality. You need to have an object in the scene.



### *Insert Keyframe*

Opens a menu where you can insert a keyframe with a defined keying set.

### *Delete Keyframes*



Deletes keyframes at the current frame.

### *Clear Keyframes*

Deletes all keyframes.

### *Change Keying Set*


Opens a menu where you can change the keying set.



## In-Between

### In Between

In Between are tools to influence the look of the pose between the keyframes.



For example, record a keyframe at frame 1, then record a keyframe at frame 20. Then go to frame 10, and activate one of the tools. Now you can play around with the settings. And when you are satisfied with the result then you can record a keyframe at this position.

### Header values

When you activate one of the tools, then you will see a percentage slider in the header. This slider is not interactive. It just displays the percentage of the exaggeration.



### Footer hotkey display

In the footer you will see some hotkeys for further options. These hotkeys are hard coded, and cannot be changed in the input manager.

Breakdown: W/E/R/B/C - Limit to Transform/Property Set | S - Enable overshoot | Shift - Hold for precision | Ctrl - Hold for 10% increments | [H] - Toggle bone visibility

The hotkeys W, E and R stands for the usual transform modes move, rotate or scale. Hotkey B stands for Bendy Bones. And C is for a custom property.

Overshoot allows you to go over the 0 -100 per cent range. The header values shows a bigger range then.



The rest of the hotkeys should be self explaining.


### Push Pose from Rest Pose

Exaggerates the current pose. Pushes the current pose further away from the rest pose.

#### Last Operator Push Pose from Rest Pose

##### Percentage

The percentage of exaggeration.



##### Previous Keyframe

The keyframe position before the current frame.




## ***Next Keyframe***

The keyframe position after the current frame.


## ***Channels***

Limit the push effect to specific channels.



## ***Axis Lock***

Limit the push effect to specific axis.




## **Relax Pose to Rest Pose**

Relaxes the current pose towards the Rest pose.

## **Last Operator Relax Pose to Rest Pose**

### ***Percentage***

The percentage of relaxing.



### ***Previous Keyframe***


The keyframe position before the current frame.

### ***Next Keyframe***

The keyframe position after the current frame.


### ***Channels***

Limit the relax effect to specific channels.



### ***Axis Lock***

Limit the relax effect to specific axis.



## **Push Pose from Breakdown**

Exaggerates the current pose. Pushes the current pose further away from the previous pose.

## Last Operator Push Pose

### **Percentage**

The percentage of exaggeration.

### **Previous Keyframe**

The keyframe position before the current frame.

### **Next Keyframe**




The keyframe position after the current frame.

### **Channels**

Limit the push effect to specific channels.

### **Axis Lock**

Limit the push effect to specific axis.



## Relax Pose to Breakdown

Relaxes the current pose.

## Last Operator Relax Pose to Breakdown

### **Percentage**

The percentage of relaxing.

### **Previous Keyframe**



The keyframe position before the current frame.

### **Next Keyframe**

The keyframe position after the current frame.


### **Channels**

Limit the relax effect to specific channels.



## Axis Lock

Limit the relax effect to specific axis.



## Pose Breakdowner

Creates a suitable breakdowner pose on the current frame.

### Last Operator Pose Breakdowner

#### Percentage

The percentage of exaggeration.

#### Previous Keyframe

The keyframe position before the current frame.

#### Next Keyframe




The keyframe position after the current frame.

#### Channels

Limit the breakdowner pose to specific channels.

#### Axis Lock

Limit the breakdowner pose to specific axis.




## Propagate

The Propagate tool automates the process of copying and pasting between keyframes. It copies the pose of the selected bones on the current frame over to the keyframes by the chosen Termination mode in the Last Operator Propagate Pose.

The different Propagate methods can be adjusted in the Last operator too. Here you will find even more methods. The menu just lists the common ones.

The methods are quite self explaining, but are explained in the last operator section.



Usage example with Termination mode "On Selected Keyframes".

Create a little armature.

Set a keyframe at frame 0.

Set a keyframe at frame 20.

Pose frame 20.

Set a keyframe at frame 40. It will most probably be identical with Frame 20.

Now select those Keyframes at position 40 in the Dope Sheet Editor.

Set position to Frame 0.


Press Propagate, and in the Last operator Propagate Pose choose On Selected Keyframes.

The selected keyframes at frame 40 will now turn into the corresponding keyframes from position 0.

## Last Operator Propagate Pose

### Terminate Mode

A drop down box where you can choose between different termination modes for Propagate.



### *While Held*

While held it tries to guess when to stop propagating by examining the pauses in the animation curves per control (This means all F-Curves for a bone instead of per F-Curve).

### *To Next Keyframe*

Copies the pose to the first keyframe after the current frame.

### *To Last Keyframe*

Replaces the last keyframe.

### *Before Frame*

Copies to all keyframes between current frame and the End frame option.

### *Before Last Keyframe*

To all keyframes from current frame until no more are found.

### *On Selected Keyframes*

Applies the pose of the selected bones to all selected keyframes.

### *On Selected Markers*

Copies to all keyframes on frames with Scene Markers after the current frame.

### End Frame

Defines the end frame for the Propagate.

## Single Operators

### Copy Pose

Copies the current pose. You copy what you have selected.



### Paste Pose

Pastes a previous copied pose.


### Paste Pose Flipped

Pastes a previous copied pose, but flipped along X axis.

### Last Operator Paste Pose

#### *Flipped on X Axis*

Paste the pose flipped along X Axis.




#### *On Selected Only*

Paste just on the selected bones. Not on the unselected.

## Pose Library


The content of this menu belongs to the Pose library. Which can be found in the Properties editor.



### Browse Poses

With this feature you can browse through the available poses in the 3D view. While operation you will see informations in the header. It shows you what the current pose is, and how to navigate to the next or previous pose.


Note that you need to have the bones selected for which you want to display the poses. When in doubt, select all bones.



### Last Operator Pose lib Browse Poses

#### Pose


Scroll through the poses.



## Add Pose

Add a new pose for your armature to the pose library.

Note that you need to have the bones selected for which you want to add the pose. It just records the pose for the selected bones.



Calling the tool opens a popup where you can choose how you want to add the current pose.

### Add New

Adds a new pose.

### Add New (Current Frame)

Adds a new pose at the current frame. It does NOT record a keyframe.

### Replace Existing

Replace an existing pose.

### Last Operator Pose Lib Add Pose

#### Frame

The frame at which this pose should be created



#### Pose Name

Rename the pose while creation.

## Rename Pose


Rename a pose. It opens a popup menu where you can choose the pose to rename, and here you can rename it. One pose at a time.



### Last Operator Pose Lib Rename Pose

#### New Pose Name

Enter the new pose name.




#### Pose

Choose the pose that you want to rename.

## Remove Pose


Removes the currently active pose. The tool opens a popup where you can choose the pose to remove.



## Last Operator Pose Lib Remove Pose

### Pose

Choose which pose to remove.




Attention! This dialog is bugged. When you have two animations in the library and remove one, then the box shows empty. When you now switch to the other pose here, then you remove both poses. There is no way back, since you can't select the previous pose anymore.

---

## Motion Paths


Objects can be animated. Let's say you send them from a to b to c. The object will move to b, then to c. Some kind of a path. This path is not visible by default.

With motion paths you can calculate this path, and make it visible.



## Calculate

Calculates the motion path of the selected object. It opens a panel to define the start and end frame of the calculation.



## Last Operator Calculate Object Path

### Start

Defines the start frame of the calculation.


### End

Defines the end frame of the calculation.

### Bake Location

Where to draw the curve. At the head or at the tail of the bone(s)

---





## Clear


Clear remove the motion path from the object.

---

## Bone Groups

Bone Groups is a menu to handle bone group functionality from within a menu in the 3D view. The bone groups themselves can be found in the Properties editor.





## Assign to New Group


Assigns the selected bone(s) to a new group.

## Assign to Group

Assigns the selected bone(s) to an existing group.

## *Last operator Add Selected to Bone Group*

This last operator belongs to both tools. Assign to New Group, and Assign to Group.



## Bone Group Index

Adjust the Bone Group Index. An Index of 0 creates a new bone group. Higher values tries to assign the bone to existing bone groups instead.

## Remove selected from Bone Groups

Removes the selected bone(s) from the assigned bone groups.


## Remove Bone Group

Removes the currently active bone group.

## Parent

Parenting the skin or other armatures happens in Object mode. You can also parent in Pose Mode. It just does not make much sense since you need to enter Object mode for one of the objects anyways. The only somehow relevant settings in the parenting menu here is clear parent. But even this is better done in Object Mode.


The parenting menu is already explained in the Object menu in Object mode. So we won't repeat the whole description here.





## Inverse Kinematics

Inverse Kinematics is a menu with two isolated items from the whole bone constraints menu. The Inverse Kinematics. You could also add an Inverse Kinematics bone constraint by the Constraints / Add (With Targets) menu item from above. It is in the list. But this menu allows quick access without big search.






### Add IK to Bone


Add IK to bone adds an IK bone constraint to the selected bone. When you add an IK constraints with just the bone selected, then it adds an empty as a handler too, and fills it in as a target.

Add IK calls a popup. When you have just one bone selected then you can choose between adding an empty as the target or to create the bone constraint without target.

When you have more than one bone selected then you can just add the constraint to the active bone.



You can define an own target object too. The armature needs to be in pose mode. Let's create a cube or another primitive. Select it. Now hold down Shift, and click at the bone where you want to add the constraint too. Then choose Add (with Targets), and choose your constraint method. The cube will now be chosen as the target object.



### Last Operator Add IK to Bone

#### With Targets

Define if you want to add the IK constraints with or without a target.




#### Remove IK

Removes all IK bone constraint(s) at the selected bone(s).

## Constraints



Constraints is a menu that contains some tools around constraints.




### Add (With Targets)

Add (With Targets) calls the Constraints menu where you can choose the constraint that you want to add. When you add an IK constraints with just the bone selected, then it adds an empty as a handler too, and fills it in as a target. Which is similar to what you can do with the Add IK to Bone from the IK menu.

But you can add more than just the IK constraint. It is the same menu that you can open by clicking at the Add Bone Constraint drop down menu in the Properties editor.



You can define an own target object too. The armature needs to be in pose mode. Let's create a cube or another primitive. Select it. Now hold down Shift, and click at the bone where you want to add the constraint too. Then choose Add (with Targets), and choose your constraint method. The cube will now be chosen as the target object.



### Copy Constraints to selected Bones

Copies the constraints with all its settings to the selected bone.

#### Usage:

Select the bone where you want to copy the constraints to. Hold down shift, then select the bone that contains the constraints. Then perform the tool. The constraints will be copied.

## Clear Pose Constraints

Removes all bone constraints modifiers from the bone.

## Names

Bforartists has some internal name conventions for a symmetrical armature. Bones are for example named mybone.L or mybone.R, dependant at which side of the mirror axis they are. The Names items allows you to rename the bone names to this name convention.



### Autoname Left/Right



Renames the bones from left to right.

### Autoname Front/Back

Renames the bones from front to back.

### Autoname Top/Bottom


Renames the bones from top to bottom.



### Last operator Autoname by Axis

#### Axis

Choose the autoname axis again. Left/Right is X axis, Front/Back is Y axis, and Top/Bottom is Z axis.



### Flip Names

When you mirror a half of an armature you end in names like Bone.001.R.001. But what we need is Bone.001.L for a symmetrical armature. Flip names flips the names to follow the left right name conventions.

### Last operator Flip Names


#### Strip Numbers

Tries to remove the numbers in the names if possible.



## Flip Quats

This feature flips the quaternion rotation values of the currently selected bone(s). Positive values becomes negative, and negative values becomes positive.



## Change Armature Layers

Armature and bones has its own layer system. This menu item opens a popup where you can put the whole armature onto another layer.



## Last Operator Change Armature Layers


### *Layer*

Put the armature onto another layer.



## Change Bone Layers


Armature and bones has its own layer system. This menu item opens a popup where you can put single selected bone(s) onto another layer.



## Last Operator Change Bone Layers

### *Layer*

Put the selected bones onto another layer.



## Show/Hide

Show or hide the selected geometry

### **Show Hidden**

Makes all hidden geometry visible again.

### **Hide Selected**

Hides the selected geometry.


## Hide Unselected

Hides the not selected geometry. The selected geometry stays visible.

---

## Bone Settings

Bone Settings is a menu with menu items to toggle special check boxes in the Properties editor. But here you can do it for a selection too, and not just one object.



## Last Operator Collection Boolean Set

Each of the menu items uses the same Last Operator. With different strings for the booleans.

